





New-User Intro to Design-Expert® Software



Richard Williams
BScHE, MSM, Six Sigma MBB
May 7, 2025

Making the most of this learning opportunity

 Hide the Control Panel
  Mute your line
 

To prevent audio disruptions, all attendees will be muted.

During the webinar, questions will be monitored in the GoToWebinar questions pane (We'll try to get to as many as possible)

Questions can be sent to stathelp@statease.com. Please provide your company name and, if you are using Design-Expert, the serial number (found under Help, About).

The slides and a recording of this webinar will be posted on the Stat-Ease Webinars page within a few business days.

DX Software Intro for New Users



2

Goals



- Why consider design of experiment (DOE) methods
- Introduction to Design-Expert by demonstration (“demo”)
- Awareness of applications and design types
- Next steps

Please press the raise hand button on your GotoWebinar control panel if you are with me.



DX Software Intro for New Users

3

Stat-Ease, Inc.



Design of Experiments Software and Training
www.statease.com

STAT-EASE 360
DESIGNEXPERT

 **STAT-EASE
ACADEMY**

DX Software Intro for New Users

4

Agenda



- DOE – What's in it for me? (WIIFM)
- Factorial demo—characterizing vital interactions
- Response surface method (RSM) demo—optimization
- Mixture design—specialized tools to hit the sweet spot
- Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount

DX Software Intro for New Users

5

Agenda



- **DOE – What's in it for me? (WIIFM)**
- Factorial demo—characterizing vital interactions
- Response surface method (RSM) demo—optimization
- Mixture design—specialized tools to hit the sweet spot
- Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount

DX Software Intro for New Users

6


DOE WIIFM: What is a Designed Experiment?



- Design of experiments (DOE) is a planned approach for determining cause and effect relationships

- It benefits from multifactor testing rather than evaluating one factor at a time (OFAT)

- DOE can identify factor interactions!



DX Software Intro for New Users


7

DOE WIIFM Why do design of experiments?



- OFAT experimentation cannot identify factor interactions which frequently play a key role in process improvement, e.g., time and temperature affecting your yield of cookies—too much of both will burn them, not enough leaves them unbaked.*
- DOE multifactorial experimentation by its parallel processing provides more information in fewer runs than OFAT (an inefficient and old-fashioned serial method)
- DOE statistics provide confidence in the findings

*Source of graphic: [https://en.wikipedia.org/wiki/Interaction_\(statistics\)](https://en.wikipedia.org/wiki/Interaction_(statistics))




DX Software Intro for New Users

8

DOE WIIFM SCO Strategy of Experimentation



Design-Expert provides a full array of designs and analysis tools to address three overarching goals:



- Screen for vital few process factors or mixture components
- Characterize critical interactions
- Optimize for peak performance

DX Software Intro for New Users

9

DOE Process



1. Define objective in terms of measurable responses
2. Select the input factors to study
3. Select your design (the layout of factor levels run-by-run)
4. Conduct the experiment (the hard part!)
5. Analyze the results using your software's statistical tools
6. Diagnose the residuals for abnormalities and outliers
7. Interpret the outcomes using model graphs
8. Optimize factors for maximum desirability of multiple responses
9. Test your predictive model via confirmation runs
10. Celebrate!

DX Software Intro for New Users

10

Agenda



- DOE – What's in it for me? (WIIFM)
- **Factorial demo—characterizing vital interactions**
- Response surface method (RSM) demo—optimization
- Mixture design—specialized tools to hit the sweet spot
- Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount

DX Software Intro for New Users

11

Reactor Case Study

2⁵ Full Factorial



Find the conditions that maximize yield of a chemical reaction.

There are five key factors that the engineers chose:

- A. Feed rate, 10-15 l/min
- B. Catalyst level, 1-2 wt %
- C. Agitation rate, 100-120 rpm
- D. Temperature, 140-180 deg C
- E. Atmosphere, nitrogen or air*

**Saves time not having to batten down the hatch.
But will the air ruin the reaction? Let's find out!*



DX Software Intro for New Users

12

Reactor Case Study

2⁵ Full Factorial



- Objective: Maximize yield
- Parameters for calculating power
Ensures that design will likely succeed if
 - ❖ Signal (Δy) = 3 %
Any improvement less than this will be unimportant
 - ❖ Noise (σ) = 2 %
The variability in the reaction, sampling and testing



*rsd reactor.dxp
Rebuild (show power!) and analyze*

DX Software Intro for New Users

13

Factorial Design Summary

Things to Remember



- Full-factorial designs test all possible factor combinations. They characterize all effects: main, two-factor interactions (2fi's), etc.
- Power assesses the probability an experimental design will identify important effects. It is driven by the signal-to-noise ratio ($\Delta y/\sigma$). Ideally power will be in the range of 80 to 95%, i.e., with just the right number of runs, not too few and not too many.

DX Software Intro for New Users


14

Factorial Design Summary

Tip 



- Consider saving time and resources via fractionation. For example, the 32-run reactor experiment could be cut in half and still characterize 2fi's. But be wary of loss of power and resolution. Green is good, yellow OK (for screening) and red best avoided (other than ruggedness testing)



	2	3	4	5	6	7
4	2^2	2^{3-1}_{III}				
8		2^3	2^{4-1}_{IV}	2^{5-2}_{III}	2^{6-3}_{III}	2^{7-4}_{II}
16			2^4	2^{5-1}_{V}	2^{6-2}_{IV}	2^{7-3}_{IV}
32				2^5	2^{6-1}_{VI}	2^{7-2}_{IV}
64					2^6	2^{7-1}_{VII}

DX Software Intro for New Users

15

Agenda



- DOE – What's in it for me? (WIIFM)
- Factorial demo—characterizing vital interactions
- **Response surface method (RSM) demo—optimization**
- Mixture design—specialized tools to hit the sweet spot
- Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount


DX Software Intro for New Users

16


Response Surface Method Designs Handling “Pure” Curvature



Two-factor interactions
twists in the plane
 $y=10+6AB$




Squared terms
symmetric curvature
 $y=19+3A-3B-6A^2-6B^2$



DX Software Intro for New Users

17

Reaction Case Study RSM (Central Composite Design)



Engineers hope to find conditions that maximize conversion while also keeping activity within a target range.

There are three key factors you think are important

- A. Time, 40-50 minutes
- B. Temperature, 80-90 deg C
- C. Catalyst, 2-3 wt %

Goals: Achieve greater than 80% conversion and maintain activity between 60 and 66, with 63 being ideal.

The engineers believe the optimal conditions will be in the interior of the design space.


DX Software Intro for New Users

18

Reaction Case Study RSM (Central Composite Design)



- Objective: maximize conversion and target activity
- Responses: Conversion %, Activity
- Goals:
 - Conversion >80%
 - Activity Target 63 +/- 3



RSW RXN-a.dpx
Rebuild, model & optimize.

DX Software Intro for New Users

19

RSM Design Summary Things to Remember



- RSM designs are useful when curvature (non-linearity) is anticipated within the design space
- The model terms include quadratic (or higher) terms in addition to the main effect and interaction terms from factorial designs
- More runs will be required for RSM designs than for factorials
- Numerical and graphical optimization tools in DX find the optimal conditions to satisfy one or more criteria

DX Software Intro for New Users

20

Stat-Ease Training: Sharpen Up Your DOE Skills



Modern DOE for Process Optimization

Discover how to use factorial and RSM designs to gain process understanding and optimize your products.

Individuals	Teams (6+ people)
Improve your DOE skills	Choose your date & time
Topics applicable to both novice and advanced practitioners	Add company case studies

Learn more: www.statease.com

Contact: workshops@statease.com

DX Software Intro for New Users

21

Agenda



- DOE – What’s in it for me? (WIIFM)
- Factorial demo—characterizing vital interactions
- Response surface method (RSM) demo—optimization
- **Mixture design—specialized tools to hit the sweet spot**
- Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount

DX Software Intro for New Users

22

What Makes a Mixture?

Two Conditions



1. The factors are ingredients of a mixture.
2. The response is a function of proportions; not amounts.


*Given these two conditions,
fixing the total (an equality constraint) facilitates
modeling of the response as a function
of component proportions.*

DX Software Intro for New Users

23

Lemonade

Taste Dependent on Proportions




DX Software Intro for New Users

24

Three-Component Mixture

(e.g., an Arnie Palmer—tea added to lemonade)



DX Software Intro for New Users

25

Agenda




- DOE – What's in it for me? (WIIFM)
- Factorial demo—characterizing vital interactions
- Response surface method (RSM) demo—optimization
- Mixture design—specialized tools to hit the sweet spot
- **Optimal (custom) demo – designs for every challenge, e.g., combining mixture and amount**

DX Software Intro for New Users

26

Mixture Amount Experiments



A mixture-amount experiment is used when the response depends on both composition and amount of the mixture:

- ☒ Application of fertilizer - - Yield is a function of both the proportions of ingredients and the amount of fertilizer applied.
- ☒ Paint - - Coverage is a function of both the proportions of ingredients and the thickness of the coating applied.
- ☒ Medicine - - Effectiveness is a function of both the proportions of ingredients and the dosage prescribed.

DX Software Intro for New Users

27

Mixture-Amount Experiment Ibuprofen Coating



Pharmaceutical formulators must optimize the composition and the amount of latex coating on a controlled-release ibuprofen. The total solids content is 31% w/v, comprised of three components:

- A) EA [Ethylacrylate] (7 to 20%)
- B) MMA [Methylmethacrylate] (7 to 20%)
- C) TEC [Triethyl Citrate] (4 to 14%)



The amount of latex coated on to a fixed number of tablets is :

- D) Coating (15 to 25 ml)

The responses are the cumulative % of drug dissolved in 1 and 12 hours.

DX Software Intro for New Users

28

Mixture-Amount Experiment Ibuprofen Coating



- Objective: Optimize coating formulation and amount
- Goals:
 - ❖ Dissolve 10-30% (target 20%) in 1 hour
 - ❖ Dissolve 80-100% (target 90%) in 12 hours




rsw ibuprofen-a
Rebuild, model & optimize.

DX Software Intro for New Users

29

Mixture (Combined) Design Summary Things to Remember



- Mixtures have a built-in constraint: the formulation must sum to a total
- Although mainly used for optimization a la RSM designs, because of the constrained total, special approaches are needed to build DOE's for mixtures and model the results
- Design-Expert can create custom (optimal) designs that combine mixture components and process factors (e.g., time, temperature, amount, etc.)

DX Software Intro for New Users

30

Stat-Ease Training: Sharpen Up Your DOE Skills



Mixture Design for Optimal Formulations

*Master formulation studies, from screening to optimization.
Mixture-process combined designs provide even more in-depth information.*

Individuals	Teams (6+ people)
Improve your DOE skills	Choose your date & time
Topics applicable to both novice and advanced practitioners	Add company case studies

Learn more: www.statease.com

Contact: workshops@statease.com

DX Software Intro for New Users

31

Summary






- A DOE is a planned, multifactor, approach to efficiently and effectively determine cause and effect relationships.
- DOE's statistics provide power and credibility to the conclusions.
- Design-Expert software, specialized for DOE, provides a wide variety of design types and modeling tools to address virtually all experimental needs.

STAT-EASE 360 **DESIGNEXPERT**

DX Software Intro for New Users

32

References*

3rd edition 20152nd edition 20161st edition 2018

DX Software Intro for New Users


* Taylor & Francis/CRC/
Productivity Press
New York, NY.

33

How to get help Inspiring industry-specific success stories



- ❑ Case studies posted at www.statease.com under Publications





DX Software Intro for New Users

34

How to get help


Much more on-line and at your fingertips



- 
☐ Statistics Made Easy by Stat-Ease – YouTube
- ☐ Wealth of white papers and other pubs at www.statease.com.
- 
☐ In Design-Expert software press the lightbulb for Screen Tips, view reports in annotated mode, look for context-sensitive Help (right-click) or search the Help system.
- ☐ Tutorials within the Design Expert Help tab plus accompanying data sets

DX Software Intro for New Users

35



Make the most from every experiment!™

Richard Williams
stathelp@statease.com